


SOFTWARE UPDATE PROCEDURE

CPX-900 SERIES





This instruction manual describes the process to successfully update your battery tester.

Read the instruction carefully and follow the steps listed.

Note: The location of the Icons shown on the screen pictures in this procedure may be different from the real location in your battery tester due to different versions.









Device should be connected to a battery using clamps during the process.
When there is no battery connected during the second half of the update, the device may have to be rebooted at a service location.

Visual	Step-to-step procedure
	<p>To start the over-the-air update process you'll have to be connected to a stable Wi-Fi network.</p> <p>How to check? You can see if you are connected to wifi by checking if a wifi icon is visible in the main menu.</p>
	<p>Go to Messages in the Main Menu and select the message that says an update is available.</p>
	<p>The update will automatically start loading.</p> <p>Warning Make sure the device is connected to a battery, so the device won't run out of charge during the update process.</p>
	<p>The device is connecting to the network that was last used.</p> <p>Issue? If there is an issue with connecting to a network, see the following steps.</p> <p>No issue? If the device can make a connection to a Wi-Fi network without problem, the update will be performed automatically. This will take between 15-30 minutes, depending on the Wi-Fi connection.</p>

SOFTWARE UPDATE PROCEDURE

CPX-900 SERIES

Visual	Step-to-step procedure
	<p>If the device cannot directly connect to a Wi-Fi network, it will start scanning for available networks.</p>
	<p>Select the network you wish to connect to.</p>
	<p>If the network is password protected, you'll be requested to enter the Password, and click 'Save' at the right bottom corner of the screen.</p>
	<p>The device is connecting to the network that you have just selected.</p> <p>Issue? In the case you are still unable to connect to a network, you may retry once more. If still failing, please contact your nearest service partner for assistance.</p> <p>No issue? If the device can make a connection to a Wi-Fi network without problem, the update will be performed automatically. This will take between 15-30 minutes, depending on the Wi-Fi connection.</p>
	<p>The device is updating.</p> <p>Please do not move the device, or disconnect from the battery, during the update process.</p>
	<p>After the update is installed, the device will reboot.</p> <p>The device is ready to be used again.</p> <p>Issue? If you are having issues during or after the update process, please contact your nearest service partner for assistance.</p>